2025/10/28 04:32 1/3 Print Service

Print Service

The **COBI.wms Print Service** is an MS Windows service which receives commands from the Android app and triggers a print event on the Windows machine.

How it works / Limitations

Currently, the service only works in combination with Coresuite Remote Print.

The service generates XML files and puts them in a folder that is scanned by Coresuite Designer, which takes care of the actual printing. This means, you must have Coresuite Designer installed and configured correctly to pick up XML files from a specific folder.

See here for the relevant Coresuite documentation:

http://helpfiles.coresystems.ch/help/country_package/manual/en/index.html?des_configuration_batch print.htm

Only the User and Parameter Scan-Path fields need to be filled out.

Also, if you don't have Coresuite Service, then at least one SAP Business One client must be running at all times for Coresuite Designer to process the XML files. See here for information about Coresuite Service:

https://helpdesk.coresystems.ch/hc/en-us/articles/360034896353-Coresuite-Service

(If either of the above links to the Coresuite documentation don't work, please notify support@cobisoft.de so we can update this page.)

XML files that are placed into the folder will be moved automatically into a sub-folder called _executed if the print job was successful, or into a sub-folder called _error if there was a problem. (These folders are created and managed automatically by Coresuite.) In case of an error, you can open the XML file in the _error folder (with Notepad or another text editor) and see if an error message was written into it. Usually, Coresuite writes the error message into these files in the form of an XML comment, near the end of the file.

Installation

Download: cobiwms-print-service.zip

- Extract the contents of cobiwms-print-service.zip to C:\cobiwms-print-service\.
- 2. Run the following command in cmd.exe or PowerShell:
 C:\Windows\Microsoft.NET\Framework64\v4.0.30319\InstallUtil.exe
 C:\cobiwms-print-service\cobiwms-print-service.exe
- 3. Create C:\cobiwms-print-service\config.json with contents like below.
- 4. You can now start/stop the service from the MS Windows Services application.

Example config for single-tenant setup (e.g. on-premises or private cloud):

```
{
  "ListenPort": 9110,
  "TenantConfig": [
     {
        "PrintDirectory": "C:\\CoresuiteRemotePrint\\Productive"
      }
   ]
}
```

The **PrintDirectory** must correspond to the **Parameter Scan-Path** of the Coresuite Designer configuration; see above.

Example config for multi-tenant setup (e.g. public cloud):

In a multi-tenant environment, the correct AuthToken must be entered in the COBI.wms Print Settings screen for the app to be able to trigger print jobs. The token serves both to identify the tenant, and as a password to ensure that tenants running on the same cloud environment cannot accidentally or intentionally trigger print jobs for each other.

Note that the COBI.wms Print Service does not support encrypted communication. This means that if you make the TCP port of the Print Service open to the Internet, and set up COBI.wms to contact it, then the tokens will be sent unencrypted over the Internet. It is strongly advised to set up a VPN connection in this scenario to ensure encrypted communication.

Update

- 1. Stop the service.
- Extract the contents of the new ZIP file into C:\cobiwms-print-service\.
- 3. Start the service.

2025/10/28 04:32 3/3 Print Service

Uninstall

- 1. Stop the service.
- 2. Run the following command in cmd.exe or PowerShell:
 C:\Windows\Microsoft.NET\Framework64\v4.0.30319\InstallUtil.exe /u
 C:\cobiwms-print-service\cobiwms-print-service.exe

3. Delete the folder C:\cobiwms-print-service\.

From:

https://docs.cobisoft.de/wiki/ - COBISOFT Documentation

Permanent link:

https://docs.cobisoft.de/wiki/cobi.wms/print_service?rev=1671466669

Last update: 2022/12/19 17:17

